Table of Contents

Setup a CESM 1.0.x benchmark run on a generic system....1
System requirements....1
Compile NETCDF (Requirement)....1
Download CESM source code....1
Adapt configuration files....2
Create a new case....3
Change the layout....3
Set simulation length....4
Configure the case....5
Change history file output frequency of atmosphere model (cam)....5
Build the case....5
Run the model....5
Change the resolution....6
Produce a summary....6

Setup a CESM 1.0.x benchmark run on a generic system

This is a **cookbook** to setup a CESM 1.0 benchmark run on a generic (Linux) system.
See also porting CESM in the CESM user's guide:
http://www.cesm.ucar.edu/models/cesm1.0/cesm/cesm_doc/c2161.html

System requirements

- **Compilers** known to work: intel 10.1, pgi 7.2, 8.0, 9.0, (pathscale 3.2)
- **MPI** implementations known to work: openmpi 1.4, 1.5, mvapich2 1.4, 1.5
- **tcsh** CESM setup scripts are written in tcsh

Compile NETCDF (Requirement)

- See also http://www.ncl.ucar.edu/Download/build_from_src.shtml#NetCDF

- Download NETCDF

```
wget http://www.unidata.ucar.edu/downloads/netcdf/ftp/netcdf-4.1.1.tar.gz
tar xfvz netcdf-4.1.1.tar.gz
cd netcdf-4.1.1
```

- Compile netcdf with the compiler you use later to compile the model. For example for intel compiler do:

```
export FC=ifort
export F77=ifort
export F90=ifort
export CPPFLAGS="-fPIC -DpgiFortran"
./configure --prefix=/usr/local/netcdf-4.1.1-intel --disable-netcdf-4 --disable-dap
make
make test
```

- Install NETCDF

```
make install
```

Download CESM source code

- Download from NCAR SVN. A password is needed to checkout. Please register at: http://www.cesm.ucar.edu/models/cesm1.0/register/register_cesm1.0.cgi In case you don't have time to register ask urs.beyerle@env.ethz.ch

```
svn export https://svn-ccsm-release.cgd.ucar.edu/model_versions/cesm1_0_2 cesm1_0_2
```

Adapt configuration files

- Change to **`Machines`** directory

```
cd cesm1_0_2
cd scripts/ccsm_utils/Machines/
```

- Meaning of filenames

Filename	Purpose
env_machopts.*	Set environment: Can be used to set paths to compiler, MPI library, NETCDF library
Macros.*	Set compiler name and paths to MPI library, NETCDF library. Set compiler options
mkbatch.*	Setting for queuing system

where * corresponds to a machine.

- As starting point take configuration files of a machine that is close to your environment. For example if you run on Linux, have a look at brutus_io, brutus_im, brutus_po or brutus_pm where i=intel, p=pgi, o=openmpi, m=mvapich2. You can get a list of pre-configured machines with

```
cd cesm1_0_2/scripts
./create_newcase -l
```

- Let's assume you use intel and openmpi, start with **`*.brutus_io`** files:

```
cp env_machopts.brutus_io env_machopts.your_machine
cp Macros.brutus_io       Macros.your_machine
cp mkbatch.brutus_io      mkbatch.your_machine
```

- Add to **`config_machines.xml`** a configuration tag for your machine (your_machine) - only the important lines are listed below

```
<machine MACH="your_machine"
         DESC="Test System"
         EXEROOT="/scratch/$CCSMUSER/$CASE"
         OBJROOT="$EXEROOT"
         INCROOT="$EXEROOT/lib/include"
         DIN_LOC_ROOT_CSMDATA="/scratch/cesm1/inputdata"
         DIN_LOC_ROOT_CLMQIAN="/scratch/cesm1/inputdata/atm/datm7/atm_forcing.datm7.
         BATCHQUERY="qstat -f"
         BATCHSUBMIT="qsub"
         GMAKE_J="4"
         MAX_TASKS_PER_NODE="4"
         MPISERIAL_SUPPORT="FALSE" />
```

please set the following variables:

```
EXEROOT=                    # working directory, final location of binary and outpu
DIN_LOC_ROOT_CSMDATA=       # input data, date will be downloaded on the fly
DIN_LOC_ROOT_CLMQIAN=       # input data, data will be downloaded on the fly
MAX_TASKS_PER_NODE=         # define cores per node
```

- Configure **mpirun** execution: Search in **`mkbatch.your_machine`** for the line starting the executable **`ccsm.exe`** and replace it with the correct mpirun command for your system, for example something like

```
mpirun -np ${maxtasks} ./ccsm.exe >&! ccsm.log.\$LID
# or
mpirun -x LD_LIBRARY_PATH -np ${maxtasks} ./ccsm.exe >&! ccsm.log.\$LID
```

Create a new case

- Change to **`scripts`** directory

```
cd cesm1_0_2
cd scripts
```

- Define the machine type (MACH), resolution (RES), compset (COMP=B: fully coupled model)

```
MACH=your_machine
COMP=B
RES=1.9x2.5_gx1v6
```

Possible values for RES are **T31_gx3v7** (~3°), **1.9x2.5_gx1v6** (2°) or **0.9x1.25_gx1v6** (1°).

- Define a case name (in principle, can be any name)

```
CASE=$RES-$COMP-benchmark
```

- Create case

```
./create_newcase -res $RES -compset $COMP -mach $MACH -case $CASE
```

Change the layout

- The layout will define which model component (ATM, LND, ICE, OCN, CPL) will run on how many cores.
- To **change the layout** you don't have to recreate the case (but you can if you like).
- Change into case directory

```
cd $CASE
```

- Clean the case

```
./configure -cleanmach
```

- Configure layout (all components will run on all cores)

```
NTASKS=16 #or# NTASKS=32 #or# NTASKS=64 #or# NTASKS=128 #or# NTASKS=256 #or# NTASKS=

./xmlchange -file env_mach_pes.xml -id NTASKS_ATM -val $NTASKS
./xmlchange -file env_mach_pes.xml -id NTASKS_LND -val $NTASKS
./xmlchange -file env_mach_pes.xml -id NTASKS_ICE -val $NTASKS
./xmlchange -file env_mach_pes.xml -id NTASKS_OCN -val $NTASKS
./xmlchange -file env_mach_pes.xml -id NTASKS_CPL -val $NTASKS
./xmlchange -file env_mach_pes.xml -id NTASKS_GLC -val 1
./xmlchange -file env_mach_pes.xml -id TOTALPES   -val $NTASKS
./xmlchange -file env_mach_pes.xml -id ROOTPE_OCN -val 0
```

- **Exception**: For resolution **T31_gx3v7** with **NTASKS=32**, **NTASKS=64**

```
NTASKS=32 #or# NTASKS=64

NTASKS_ATM=24
NTASKS_OCN=8
NTASKS_LND=24
NTASKS_ICE=20
NTASKS_CPL=24
NTASKS_TOTAL=32
F=$(( $NTASKS / $NTASKS_TOTAL ))
./xmlchange -file env_mach_pes.xml -id ROOTPE_GLC -val 0
./xmlchange -file env_mach_pes.xml -id NTASKS_GLC -val 1
./xmlchange -file env_mach_pes.xml -id ROOTPE_ATM -val 0
./xmlchange -file env_mach_pes.xml -id NTASKS_ATM -val $(( $NTASKS_ATM * $F ))
./xmlchange -file env_mach_pes.xml -id ROOTPE_LND -val 0
./xmlchange -file env_mach_pes.xml -id NTASKS_LND -val $(( $NTASKS_LND * $F ))
./xmlchange -file env_mach_pes.xml -id ROOTPE_ICE -val 0
./xmlchange -file env_mach_pes.xml -id NTASKS_ICE -val $(( $NTASKS_ICE * $F ))
./xmlchange -file env_mach_pes.xml -id ROOTPE_OCN -val $(( $NTASKS_ATM * $F ))
./xmlchange -file env_mach_pes.xml -id NTASKS_OCN -val $(( $NTASKS_OCN * $F ))
./xmlchange -file env_mach_pes.xml -id ROOTPE_CPL -val 0
./xmlchange -file env_mach_pes.xml -id NTASKS_CPL -val $(( $NTASKS_CPL * $F ))
./xmlchange -file env_mach_pes.xml -id TOTALPES   -val $NTASKS
```

Set simulation length

- In general, CESM is hardwired to generate monthly average data. In principle this can be turned of but needs a lot of code changes. Therefore it's not considered here. The following two cases are suggested instead:

- **CASE 1**: Run a short simulation (10 days) with producing no restart files (REST_OPTION=never) and no archiving (DOUT_S=FALSE)

```
./xmlchange -file env_run.xml -id STOP_OPTION -val 'ndays'
./xmlchange -file env_run.xml -id STOP_N      -val '10'
./xmlchange -file env_run.xml -id REST_OPTION -val 'never'
./xmlchange -file env_run.xml -id DOUT_S      -val 'FALSE'
```

- **CASE 2**: Run a longer simulation (1 months) with producing restart files at the end

```
./xmlchange -file env_run.xml -id STOP_OPTION -val 'nmonths'
./xmlchange -file env_run.xml -id STOP_N      -val '1'
./xmlchange -file env_run.xml -id REST_OPTION -val '$STOP_OPTION'
./xmlchange -file env_run.xml -id DOUT_S      -val 'FALSE'
```

Configure the case

- Configure case

```
./configure -case
```

Change history file output frequency of atmosphere model (cam)

- **CASE 1**: leave the default which is monthly output data
- **CASE 2**: change history file output frequency to **one hour**. Edit **`Buildconf/cam.buildnml.csh`** and set just after **`&cam_inparm`** the variable **nhtfrq = -1**

```
cat Buildconf/cam.buildnml.csh
...
&cam_inparm
 nhtfrq  = -1
 absems_data            = '$DIN_LOC_ROOT/atm/cam/rad/abs_ems_factors_fastvx.c030508.
...
```

In case you change **`Buildconf/cam.buildnml.csh`**, you can not go back by just deleting the lines. **You have configure an new case** with with **`./create_newcase`** !

Build the case

- Build and compile the model

```
./$CASE.$MACH.build
```

Run the model

- Run the model, for example with LSF **queuing system**

```
bsub < $CASE.$MACH.run
```

- To start without a queuing system just execute:

```
./$CASE.$MACH.run
```

- Timing results can be found after the run has been successfully completed in folder **`timing`**

```
cat timing/ccsm_timing.$CASE.*
...
Model Throughput:         6.39   simulated_years/day
...
```

Change the resolution

- Recommended resolutions are T31_gx3v7 (~3°), 1.9x2.5_gx1v6 (2°), 0.9x1.25_gx1v6 (1°)
- Create for each resolutions a separate cases !

Produce a summary

- Create performance matrix for **CASE 1** and **CASE 2**. Fill in Model Throughput in **simulated_years/day**

- **CASE 1**: Run a short simulation with producing almost no output (I/O) - Values are from **brutus.ethz.ch**

resolution / layout (NTASKS)	16	32	64	128	192	256	512
T31_gx3v7	12.0	18.3	26.9	--	--	--	--
1.9x2.5_gx1v6	--	2.27/2.60					--
0.9x1.25_gx1v6	--	--	1.88				

- **CASE 2**: Run a longer simulation with producing hourly output data - Values are from **brutus.ethz.ch**

resolution / layout (NTASKS)	16	32	64	128	192	256	512
T31_gx3v7	7.9	10.8	13.6	--	--	--	--
1.9x2.5_gx1v6	--						--
0.9x1.25_gx1v6	--	--					

Edit | Attach | Print version | History: %REVISIONS% | Backlinks | Raw View | More topic actions

Topic revision: r22 - 27 Jun 2013 - 14:51:14 - UrsBeyerle

- . Climphys

- Log In

- **Climphys Web**
- Create New Topic
- Index
- Search
- Changes
- Notifications
- RSS Feed
- Statistics
- Preferences
- **Webs**
- Public
- System

Copyright © by the contributing authors. All material on this collaboration platform is the property of the contributing authors.
Ideas, requests, problems regarding Wiki? Send feedback