

Table of Contents

VarADDTOHEAD.....	1
ADDTOHEAD.....	1

VarADDTOHEAD

You are here: Wiki >System Web>VarADDTOHEAD (09 Jan 2009, ProjectContributor)EditAttach

ADDTOHEAD

You can write `%ADDTOHEAD{ . . . }%` in a topic or template. This variable accepts the following parameters:

- `_DEFAULT` optional, id of the head block. Used to generate a comment in the output HTML.
- `text` optional, text to use for the head block. Mutually exclusive with `topic`.
- `topic` optional, full Foswiki path name of a topic that contains the full text to use for the head block. Mutually exclusive with `text`. Example: `topic="System.MyTopic"`.
- `requires` optional, comma-separated list of id's of other head blocks this one depends on.

`%ADDTOHEAD%` expands in-place to the empty string, unless there is an error in which case the variable expands to an error string.

Use `%RENDERHEAD%` to generate the sorted head tags.

Edit | Attach | Print version | History: `%REVISIONS%` | Backlinks | Raw View | More topic actions
Topic revision: r1 - 09 Jan 2009 - 13:00:00 - ProjectContributor

-  System
- Log In
- **Toolbox**
 -  Users
 -  Groups
 -  Index
 -  Search
 -  Changes
 -  Notifications
 -  RSS Feed
 -  Statistics
 -  Preferences
- **User Reference**
 - BeginnersStartHere
 - TextFormattingRules
 - Macros
 - FormattedSearch
 - QuerySearch
 - DocumentGraphics
 - SkinBrowser
 - InstalledPlugins
- **Admin Maintenance**
 - Reference Manual
 - AdminToolsCategory

- InterWikis
- ManagingWebs
- SiteTools
- DefaultPreferences
- WebPreferences

- **Categories**

- Admin Documentation
- Admin Tools
- Developer Doc
- User Documentation
- User Tools

- **Webs**

- Public
- System

•

•



Copyright © by the contributing authors. All material on this site is the property of the contributing authors.

Ideas, requests, problems regarding Wiki? Send feedback